

# MW41 Sounding System – Software Version Number

- For finding MW41 Sounding System software version number in the user interface, select Administration/Diagnostics.
- For finding MW41 Sounding System software version number from an archived sounding data set, proceed as follows:
  1. Find the compressed sounding data set \*.mwx file
  2. Open Soundings.xml file
  3. Find the software version from the file content, that is, SoftwareVersion="MW41 2.0.0"
- MW41 Sounding System software version number is automatically generated to BUFR message into the field: Additional 309052 data – Software identification and version number descriptor 025061.
  - For MW41 Sounding System the format is: MW41 2.0.0